



Windows PowerShell Get-Help on Cmdlet 'Remove-AzRecoveryServicesAsrNetworkMapping'

PS:\>Get-HELP Remove-AzRecoveryServicesAsrNetworkMapping -Full

NAME

Remove-AzRecoveryServicesAsrNetworkMapping

SYNOPSIS

Deletes the specified ASR network mapping from the Recovery Services vault.

SYNTAX

```

Remove-AzRecoveryServicesAsrNetworkMapping [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

DESCRIPTION

The Remove-AzRecoveryServicesAsrNetworkMapping cmdlet deletes the specified ASR network mapping.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping>

The input object to the cmdlet: The ASR network mapping object corresponding to the ASR network mapping to be deleted.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False

Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1 -----

```
$currentJob = Remove-AzRecoveryServicesAsrNetworkMapping -NetworkMapping $networkmapping
```

Starts the deletion of specified ASR network mapping and returns the ASR job used to track the operation.

<https://learn.microsoft.com/powershell/module/az.recoveryservices/remove-azrecoveryservicesasrnetworkmapping>

Get-AzRecoveryServicesAsrNetworkMapping

New-AzRecoveryServicesAsrNetworkMapping