



Windows PowerShell Get-Help on Cmdlet 'Remove-AzRecoveryServicesAsrRecoveryPlan'

PS:\>Get-HELP Remove-AzRecoveryServicesAsrRecoveryPlan -Full

NAME

Remove-AzRecoveryServicesAsrRecoveryPlan

SYNOPSIS

Deletes the specified ASR recovery plan from Recovery Services vault.

SYNTAX

```

Remove-AzRecoveryServicesAsrRecoveryPlan [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Remove-AzRecoveryServicesAsrRecoveryPlan [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
    <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

```

DESCRIPTION

The Remove-AzRecoveryServicesAsrRecoveryPlan cmdlet deletes the specified recovery plan from the Recovery

Services vault.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan>

The input object to the cmdlet: The ASR recovery plan object corresponding to the recovery plan to be deleted.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the recovery plan to be deleted.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

----- Example 1 -----

```
$currentJob = Remove-AzRecoveryServicesAsrRecoveryPlan -RecoveryPlan $RP
```

Starts the deletion of specified recovery plan and returns the ASR job used to track the operation.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/remove-azrecoveryservicesasrrecoveryplan>

Get-AzRecoveryServicesAsrRecoveryPlan

New-AzRecoveryServicesAsrRecoveryPlan

Update-AzRecoveryServicesAsrRecoveryPlan