



## ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzRecoveryServicesResourceGuardMapping'***

***PS:\>Get-HELP Remove-AzRecoveryServicesResourceGuardMapping -Full***

### **NAME**

Remove-AzRecoveryServicesResourceGuardMapping

### **SYNOPSIS**

Deletes the resource guard mapping added to the recovery services vault.

### **SYNTAX**

```
Remove-AzRecoveryServicesResourceGuardMapping [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Token  
<System.String>] [-VaultId <System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

### **DESCRIPTION**

This cmdlet deletes the mapping between the RS vault and resource guard

### **PARAMETERS**

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-Token <System.String>

Auxiliary access token for authenticating critical operation to resource guard subscription

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-VaultId <System.String>

ARM ID of the Recovery Services Vault.

Required? false  
Position? named  
Default value None  
Accept pipeline input? True (ByValue)  
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

System.String

## OUTPUTS

System.Object

## NOTES

Example 1 Delete the resource guard mapping in a cross tenant scenario

```
$token = (Get-AzAccessToken -TenantId "xxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx").Token
```

```
Remove-AzRecoveryServicesResourceGuardMapping -VaultId $vault.ID -Token $token
```

The first command fetches the access token for the resource guard tenant where the resource guard is present. The second command deletes the mapping between the

RSVault \$vault and the resource guard. Please note that token parameter is optional and only needed to authenticate cross tenant protected operations.

## RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/remove-azrecoveryservicesresourceguardmapping>