



Windows PowerShell Get-Help on Cmdlet 'Remove-AzRecoveryServicesVault'

PS:\>Get-HELP Remove-AzRecoveryServicesVault -Full

NAME

Remove-AzRecoveryServicesVault

SYNOPSIS

Deletes a Recovery Services vault.

SYNTAX

```
Remove-AzRecoveryServicesVault [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Vault  
<Microsoft.Azure.Commands.RecoveryServices.ARSVault> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzRecoveryServicesVault cmdlet deletes a Recovery Services vault.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Vault <Microsoft.Azure.Commands.RecoveryServices.ARSVault>

Specifies an Azure Site Recovery vault object.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.ARSVault

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.VaultOperationOutput

NOTES

----- Example 1 -----

Remove-AzRecoveryServicesVault -Vault \$vault

Deletes a Recovery Services vault.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.recoveryservices/remove-azrecoveryservicesvault>

Get-AzRecoveryServicesVault

Get-AzRecoveryServicesVaultSettingsFile

New-AzRecoveryServicesVault