



Windows PowerShell Get-Help on Cmdlet 'Remove-AzRestorePoint'

PS:\>Get-HELP Remove-AzRestorePoint -Full

NAME

Remove-AzRestorePoint

SYNOPSIS

This cmdlet can remove a Restore Point

SYNTAX

```
Remove-AzRestorePoint [-ResourceGroupName] <System.String> [-Name] <System.String>
[-RestorePointCollectionName] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

This cmdlet can remove a Restore Point

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

Resource Name

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-RestorePointCollectionName <System.String>

Restore Point Collection Name

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSRestorePoint

NOTES

----- Example 1 -----

```
Remove-AzRestorePoint -ResourceGroupName <String> -RestorePointCollectionName <String> -Name <String>  
-Confirm
```

Use this to Remove a Restore Point

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azrestorepoint>