



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlDatabaseInstanceFailoverGroup'

PS:\>Get-HELP Remove-AzSqlDatabaseInstanceFailoverGroup -Full

NAME

Remove-AzSqlDatabaseInstanceFailoverGroup

SYNOPSIS

Removes an Instance Failover Group.

SYNTAX

```

Remove-AzSqlDatabaseInstanceFailoverGroup [-InputObject]
<Microsoft.Azure.Commands.Sql.InstanceFailoverGroup.Model.AzureSqlInstanceFailoverGroupModel>
    [-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Force] [-PassThru] [-Confirm] [-WhatIf]
    [<CommonParameters>]

Remove-AzSqlDatabaseInstanceFailoverGroup [-ResourceGroupName] <System.String> [-Location] <System.String>
[-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]

```

`[-DefaultProfile`

`<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]`

`[-Confirm] [-WhatIf] [<CommonParameters>]`

DESCRIPTION

This command removes the Instance Failover Group with the specified name, leaving all databases intact. The listener endpoint will be unregistered from DNS.

The Instance Failover Group's primary region should be used to execute the command.

PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-Force <System.Management.Automation.SwitchParameter>`

Skip confirmation message for performing the action.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

`-InputObject <Microsoft.Azure.Commands.Sql.InstanceFailoverGroup.Model.AzureSqlInstanceFailoverGroupModel>`

The Instance Failover Group object to remove

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Location <System.String>

The name of the Local Region from which to retrieve the Instance Failover Group.

Required? true
Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

The name of the Instance Failover Group to remove.

Required? true
Position? 2
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Specifies whether to pass through cmdlet execution output.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

The Resource ID of the Instance Failover Group to remove.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Sql.InstanceFailoverGroup.Model.AzureSqlInstanceFailoverGroupModel
System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.InstanceFailoverGroup.Model.AzureSqlInstanceFailoverGroupModel

NOTES

----- Example 1 -----

Get-AzSqlDatabaseInstanceFailoverGroup -ResourceGroupName rg -Location location -Name fg |
Remove-AzSqlDatabaseInstanceFailoverGroup

Remove a Instance Failover Group.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlatabaseinstancefailovergroup>