



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlInstancePool'

PS:\>Get-HELP Remove-AzSqlInstancePool -Full

NAME

Remove-AzSqlInstancePool

SYNOPSIS

Removes an Azure SQL Instance pool.

SYNTAX

```

Remove-AzSqlInstancePool [-InputObject]
<Microsoft.Azure.Commands.Sql.Instance_Pools.Model.AzureSqlInstancePoolModel> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]

Remove-AzSqlInstancePool [-ResourceGroupName] <System.String> [-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]

Remove-AzSqlInstancePool [-ResourceId] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzSqlInstancePool cmdlet removes an Azure SQL Instance pool.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Sql.Instance_Pools.Model.AzureSqlInstancePoolModel>

The instance pool object to remove.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The name of the instance pool.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

The instance pool resource id to remove.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Sql.Instance_Pools.Model.AzureSqlInstancePoolModel

System.String

OUTPUTS

System.Object

NOTES

----- Example 1: Remove an instance pool -----

Remove-AzSqlInstancePool -ResourceGroupName resourcegroup01 -Name instancePool0

Example 2: Remove an instance pool by its resource identifier

```
Remove-AzSqlInstancePool -ResourceId
```

```
"/subscriptions/xxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx/resourceGroups/resourcegroup01/providers/Microsoft.Sql/instancePools/instancePool0"
```

Example 3: Remove an instance pool by an instance pool object

```
Get-AzSqlInstancePool -ResourceGroupName resourcegroup01 -Name instancePool0
```

```
Remove-AzSqlInstancePool -InputObject $instancePool
```

This command removes an instance pool named instancePool0.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlinstancepool>