



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlServerCommunicationLink'

PS:\>Get-HELP Remove-AzSqlServerCommunicationLink -Full

NAME

Remove-AzSqlServerCommunicationLink

SYNOPSIS

Deletes a communication link for elastic database transactions between two servers.

SYNTAX

```
Remove-AzSqlServerCommunicationLink [-ResourceGroupName] <System.String> [-ServerName] <System.String>
[-LinkName] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzSqlServerCommunicationLink cmdlet deletes a server-to-server communication link for elastic database transactions in Azure SQL Database.

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-LinkName <System.String>

Specifies the name of the server communication link that this cmdlet deletes.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group to which the server specified by the ServerName parameter belongs.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerName <System.String>

Specifies the name of a server. This server contains the communication link that this cmdlet deletes.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerCommunicationLink.Model.AzureSqlServerCommunicationLinkModel

NOTES

* Keywords: azure, azurearm, arm, resource, management, manager, sql, database, mssql

----- Example 1: Delete a communication link -----

```
Remove-AzSqlServerCommunicationLink -ResourceGroupName "ResourceGroup01" -ServerName "ContosoServer17"  
-LinkName "Link01"
```

This command deletes a server-to-server communication link named Link01 on ContosoServer17.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlservercommunicationlink>

Get-AzSqlServerCommunicationLink

New-AzSqlServerCommunicationLink

SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>

