



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlServerDisasterRecoveryConfiguration'

PS:\>Get-HELP Remove-AzSqlServerDisasterRecoveryConfiguration -Full

NAME

Remove-AzSqlServerDisasterRecoveryConfiguration

SYNOPSIS

Removes a SQL database server system recovery configuration.

SYNTAX

```
Remove-AzSqlServerDisasterRecoveryConfiguration [-ResourceGroupName] <System.String> [-ServerName]
<System.String> [-VirtualEndpointName] <System.String>
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Force] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzSqlServerDisasterRecoveryConfiguration cmdlet removes a SQL database server system recovery configuration.

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerName <System.String>

Specifies the name of a SQL database server.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VirtualEndpointName <System.String>

Specifies the name of a virtual end point.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerDisasterRecoveryConfiguration.Model.AzureSqlServerDisasterRecoveryConfigurationModel

NOTES

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlserverdisasterrecoveryconfiguration>

Get-AzSqlServerDisasterRecoveryConfiguration

New-AzSqlServerDisasterRecoveryConfiguration

Set-AzSqlServerDisasterRecoveryConfiguration

SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>