



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlServerTrustGroup'

PS:\>Get-HELP Remove-AzSqlServerTrustGroup -Full

NAME

Remove-AzSqlServerTrustGroup

SYNOPSIS

Deletes a Server Trust Group.

SYNTAX

```
Remove-AzSqlServerTrustGroup [-ResourceGroupName] <System.String> [-Location] <System.String> [-Name]
<System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Deletes a Server Trust Group with specified name, location and resource group.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Force <System.Management.Automation.SwitchParameter>

Skip confirmation message for performing the action.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Location <System.String>

The location of the Server Trust Group to remove.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

The name of Server Trust Group to remove.

Required?	true
Position?	2
Default value	None
Accept pipeline input?	False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Defines whether to return the removed Server Trust Group

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerTrustGroup.Model.AzureSqlServerTrustGroupModel

NOTES

----- Example 1 -----

Remove-AzSqlServerTrustGroup -ResourceGroupName "ResourceGroup01" -Location "West Europe" -Name "ServerTrustGroup01"

Deletes a Server Trust Group in location West Europe with name ServerTrustGroup01 in resource group ResourceGroup01.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlservertrustgroup>