



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSqlSyncMember'

PS:\>Get-HELP Remove-AzSqlSyncMember -Full

NAME

Remove-AzSqlSyncMember

SYNOPSIS

Removes an Azure SQL Database Sync Member.

SYNTAX

```
Remove-AzSqlSyncMember [-ResourceGroupName] <System.String> [-ServerName] <System.String> [-DatabaseName]
<System.String> [-SyncGroupName] <System.String>
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Force] -Name <System.String> [-PassThru] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzSqlSyncMember cmdlet removes an Azure SQL Database Sync Member.

-DatabaseName <System.String>

The name of the Azure SQL Database.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Skip confirmation message for performing the action

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The sync member name.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Defines Whether return the removed sync member

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerName <System.String>

The name of the Azure SQL Server.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-SyncGroupName <System.String>

The sync group name.

Required? true
Position? 3
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.DataSync.Model.AzureSqlSyncMemberModel

NOTES

----- Example 1: Remove a sync member -----

```
Remove-AzSqlSyncMember -ResourceGroupName "ResourceGroup01" -ServerName "Server01" -DatabaseName  
"database01" -SyncGroupName "syncGroup01" -Name "syncMember01"
```

This command removes the Azure SQL Database Sync Member named syncMember01.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/remove-azsqlsyncmember>

New-AzSqlSyncMember

Update-AzSqlSyncMember

Get-AzSqlSyncMember