



Windows PowerShell Get-Help on Cmdlet 'Remove-AzStackHCIMVirtualHardDisk'

PS:\>Get-HELP Remove-AzStackHCIMVirtualHardDisk -Full

NAME

Remove-AzStackHCIMVirtualHardDisk

SYNOPSIS

The operation to delete a virtual hard disk.

SYNTAX

```
Remove-AzStackHCIMVirtualHardDisk [-SubscriptionId <String>] -ResourceId <String> [-Force] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

```
Remove-AzStackHCIMVirtualHardDisk -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>]
[-Force] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

DESCRIPTION

The operation to delete a virtual hard disk.

PARAMETERS

-Name <String>

Name of the virtual hard disk

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceId <String>

The ARM Resource ID of the virtual hard disk.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Force [<SwitchParameter>]

Forces the cmdlet to remove the virtual hard disk without prompting for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

System.Boolean

----- EXAMPLE 1 -----

```
PS C:\>Remove-AzStackHCIVMVirtualHardDisk -Name "testVhd" -ResourceGroupName "test-rg"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.stackhcivm/remove-azstackhcivmvirtualharddisk>