



Windows PowerShell Get-Help on Cmdlet 'Remove-AzStorageQueue'

PS:\>Get-HELP Remove-AzStorageQueue -Full

NAME

Remove-AzStorageQueue

SYNOPSIS

Removes a storage queue.

SYNTAX

```
Remove-AzStorageQueue [-Name] <System.String> [-Context  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]  
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzStorageQueue cmdlet removes a storage queue.

PARAMETERS

-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>

Specifies the Azure storage context. To obtain the storage context, the New-AzStorageContext cmdlet.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of the queue to remove.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Indicates that this cmdlet returns a Boolean that reflects the success of the operation. By default, this cmdlet does not return a value.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext

OUTPUTS

System.Boolean

NOTES

----- Example 1: Remove a storage queue by name -----

```
Remove-AzStorageQueue "ContosoQueue01"
```

This command removes a queue named ContosoQueue01.

----- Example 2: Remove multiple storage queues -----

```
Get-AzStorageQueue "Contoso*" | Remove-AzStorageQueue
```

This command removes all queues with names that start with Contoso.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/remove-azstoragequeue>

[Get-AzStorageQueue](#)

[New-AzStorageQueue](#)