



Windows PowerShell Get-Help on Cmdlet 'Remove-AzStorageSyncGroup'

PS:\>Get-HELP Remove-AzStorageSyncGroup -Full

NAME

Remove-AzStorageSyncGroup

SYNOPSIS

This command will delete the specified sync group.

SYNTAX

```
Remove-AzStorageSyncGroup [-InputObject] <Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup>
[-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzStorageSyncGroup [-ResourceGroupName] <System.String> [-StorageSyncServiceName] <System.String>
[-Name] <System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzStorageSyncGroup [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
```

```
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
```

[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

This command will delete the specified sync group. A sync group can only be removed when all of the contained endpoints are deleted first.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Supply -Force to skip confirmation of this command.

Required? false

Position? named

Default value False

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup>

SyncGroup Input Object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the SyncGroup.

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

In normal execution, this cmdlet returns no value on success. If you provide the PassThru parameter, then the cmdlet will write a value to the pipeline after successful execution.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

SyncGroup Resource Id

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-StorageSyncServiceName <System.String>

Name of theStorageSyncService.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup

System.String

System.Management.Automation.SwitchParameter

OUTPUTS

System.Object

NOTES

----- Example 1 -----

```
Remove-AzStorageSyncGroup -Force -ResourceGroupName "myResourceGroup" -StorageSyncServiceName  
"myStorageSyncServiceName" -Name "mySyncGroupName"
```

This command will remove the sync group.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/remove-azstoragesyncgroup>