



Windows PowerShell Get-Help on Cmdlet 'Remove-AzSynapseSparkConfiguration'

PS:\>Get-HELP Remove-AzSynapseSparkConfiguration -Full

NAME

Remove-AzSynapseSparkConfiguration

SYNOPSIS

Removes a spark configuration from a workspace.

SYNTAX

```

Remove-AzSynapseSparkConfiguration [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]
-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSSparkConfigurationResource> [-PassThru] [-Confirm]
[-WhatIf] [<CommonParameters>]

```

```

Remove-AzSynapseSparkConfiguration [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Name
<System.String> [-PassThru] -WorkspaceName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

```

```

Remove-AzSynapseSparkConfiguration [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Name
<System.String> [-PassThru] -WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

```

[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzSynapseSparkConfiguration cmdlet removes a spark configuration from a workspace.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSSparkConfigurationResource>

The Spark configuration object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The Spark Configuration name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

This Cmdlet does not return an object by default. If this switch is specified, it returns true if successful.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

Microsoft.Azure.Commands.Synapse.Models.PSSparkConfigurationResource

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Remove-AzSynapseSparkConfiguration -WorkspaceName ContosoWorkspace -Name ContosoSparkConfiguration

Remove a spark configuration called ContosoSparkConfiguration from the workspace ContosoWorkspace.

----- Example 2 -----

\$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace

\$ws | Remove-AzSynapseSparkConfiguration -Name ContosoSparkConfiguration

Remove a spark configuration called ContosoSparkConfiguration from the workspace ContosoWorkspace through pipeline.

----- Example 3 -----

```
$sparkConfiguration = Get-AzSynapseSparkConfiguration -WorkspaceName ContosoWorkspace -Name  
ContosoSparkConfiguration
```

```
$sparkConfiguration | Remove-AzSynapseSparkConfiguration
```

Remove a spark configuration called ContosoSparkConfiguration from the workspace ContosoWorkspace through pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/remove-azsynapsesparkconfiguration>