



Windows PowerShell Get-Help on Cmdlet 'Remove-AzVMNetworkInterface'

PS:\>Get-HELP Remove-AzVMNetworkInterface -Full

NAME

Remove-AzVMNetworkInterface

SYNOPSIS

Removes a network interface from a virtual machine.

SYNTAX

```
Remove-AzVMNetworkInterface [-VM] <Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine>  
[[[-NetworkInterfaceIDs] <System.String[]>] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]  
[<CommonParameters>]]
```

DESCRIPTION

The Remove-AzVMNetworkInterface cmdlet removes a network interface from a virtual machine.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-NetworkInterfaceIDs <System.String[]>

Specifies an array of network interface IDs that this cmdlet removes.

Required?	false
Position?	1
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-VM <Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine>

Specifies the virtual machine from which this cmdlet removes a network interface. To obtain a virtual machine object, use the Get-AzVM cmdlet.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine

OUTPUTS

Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine

NOTES

----- Example 1 -----

```
Remove-AzVMNetworkInterface -VM $vmConfig  
$vmConfig.NetworkProfile
```

```
NetworkInterfaces NetworkApiVersion NetworkInterfaceConfigurations
```

```
{
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azvmnetworkinterface>

Get-AzVM