



Windows PowerShell Get-Help on Cmdlet 'Remove-AzVmGalleryApplication'

PS:\>Get-HELP Remove-AzVmGalleryApplication -Full

NAME

Remove-AzVmGalleryApplication

SYNOPSIS

Remove a VMGalleryApplication object from the PSVirtualMachine object.

SYNTAX

```

Remove-AzVmGalleryApplication [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-GalleryApplicationsReferenceId <System.String> -VM
<Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine> [-Confirm] [-WhatIf] [<CommonParameters>]

```

DESCRIPTION

Removes a VMGalleryApplication object from the PSVirtualMachine object.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-GalleryApplicationsReferenceId <System.String>

Package Reference Id of the Gallery Application to delete.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-VM <Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine>

The PSVirtualMachine object to delete a Gallery Application Reference ID from.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Compute.Models.PSVirtualMachine

NOTES

```
$vm = Get-AzVM -ResourceGroupName $rgname -Name $vmName
```

```
Remove-AzVmGalleryApplication -VM $vm -GalleryApplicationsReferenceId $refId
```

Remove gallery application by reference Id

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azvmgalleryapplication>