



Windows PowerShell Get-Help on Cmdlet 'Remove-AzVmssRunCommand'

PS:\>Get-HELP Remove-AzVmssRunCommand -Full

NAME

Remove-AzVmssRunCommand

SYNOPSIS

Remove VMSS RunCommand

SYNTAX

Remove-AzVmssRunCommand [-ResourceGroupName] <System.String> [-VMSScaleSetName] <System.String> [-AsJob]
[-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -RunCommandName
<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Remove RunCommand from the VMSS

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-ResourceGroupName <System.String>

Resource Group Name

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-RunCommandName <System.String>

Run Command Name

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False

Accept wildcard characters? false

-VMScaleSetName <System.String>

VMScaleSet Name

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSRunCommandResult

NOTES

----- Example 1 -----

```
Remove-AzVmssRunCommand -ResourceGroupName $rgname -VMScaleSetName $vmssname -Name  
myruncommand
```

Remove Run Command from Vmss

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azvmssruncommand>