



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Remove-StorageBusBinding'***

**PS:\>Get-HELP Remove-StorageBusBinding -Full**

#### **NAME**

Remove-StorageBusBinding

#### **SYNTAX**

Remove-StorageBusBinding -Guid <string> [<CommonParameters>]

Remove-StorageBusBinding -Number <uint16> [<CommonParameters>]

Remove-StorageBusBinding -PhysicalDisk <CimInstance#MSFT\_PhysicalDisk> [<CommonParameters>]

Remove-StorageBusBinding -Binding <StorageBusBinding> [<CommonParameters>]

#### **PARAMETERS**

-Binding <StorageBusBinding>

Required? true

Position? Named

Accept pipeline input? true (ByValue)

Parameter set name ByBinding

Aliases                  None

Dynamic?                false

-Guid <string>

Required?                true

Position?                Named

Accept pipeline input?    true (ByValue)

Parameter set name      ByGuid

Aliases                  Id

Dynamic?                false

-Number <uint16>

Required?                true

Position?                Named

Accept pipeline input?    true (ByValue)

Parameter set name      ByNumber

Aliases                  None

Dynamic?                false

-PhysicalDisk <CimInstance#MSFT\_PhysicalDisk>

Required?                true

Position?                Named

Accept pipeline input?    true (ByValue)

Parameter set name      ByPhysicalDisk

Aliases                  None

Dynamic?                false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,  
ErrorAction, ErrorVariable, WarningAction, WarningVariable,

`OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see  
`about_CommonParameters` (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

`System.String`  
`System.UInt16`  
`Microsoft.Management.Infrastructure.CimInstance`  
`Microsoft.Windows.Storage.StorageBusCache.StorageBusBinding`

## OUTPUTS

`System.Object`

## ALIASES

`None`

## REMARKS

Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.

-- To download and install Help files for the module that includes this cmdlet, use `Update-Help`.