



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Remove-StorageFaultDomain'

PS:\>Get-HELP Remove-StorageFaultDomain -Full

NAME

Remove-StorageFaultDomain

SYNTAX

Remove-StorageFaultDomain [-VirtualDisk] <CimInstance#MSFT_VirtualDisk> [-StorageFaultDomains <CimInstance#MSFT_StorageFaultDomain[]>]

[-StorageFaultDomainFriendlyNames <string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

Remove-StorageFaultDomain -VirtualDiskFriendlyName <string> [-StorageFaultDomains <CimInstance#MSFT_StorageFaultDomain[]>] [-StorageFaultDomainFriendlyNames <string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

Remove-StorageFaultDomain -VirtualDiskName <string> [-StorageFaultDomains <CimInstance#MSFT_StorageFaultDomain[]>] [-StorageFaultDomainFriendlyNames <string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

Remove-StorageFaultDomain -VirtualDiskUniqueId <string> [-StorageFaultDomains <CimInstance#MSFT_StorageFaultDomain[]>] [-StorageFaultDomainFriendlyNames <string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

Remove-StorageFaultDomain [-StorageTier] <CimInstance#MSFT_StorageTier> [-StorageFaultDomains
<CimInstance#MSFT_StorageFaultDomain[]>]

[-StorageFaultDomainFriendlyNames <string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob]
[<CommonParameters>]

Remove-StorageFaultDomain -StorageTierFriendlyName <string> [-StorageFaultDomains
<CimInstance#MSFT_StorageFaultDomain[]>] [-StorageFaultDomainFriendlyNames

<string[]>] [-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

Remove-StorageFaultDomain -StorageTierUniqueld <string> [-StorageFaultDomains
<CimInstance#MSFT_StorageFaultDomain[]>] [-StorageFaultDomainFriendlyNames <string[]>]

[-CimSession <CimSession>] [-ThrottleLimit <int>] [-AsJob] [<CommonParameters>]

PARAMETERS

-AsJob

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-CimSession <CimSession>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-StorageFaultDomainFriendlyNames <string[]>

Required? false

Position? Named

Accept pipeline input? false

Parameter set name ByStorageTierUniqueId, ByStorageTierFriendlyName, ByStorageTier,

ByVirtualDiskUniqueId, ByVirtualDiskName, ByVirtualDiskFriendlyName,

ByVirtualDisk

Aliases None

Dynamic? false

-StorageFaultDomains <CimInstance#MSFT_StorageFaultDomain[]>

Required? false

Position? Named

Accept pipeline input? false

Parameter set name ByStorageTierUniqueId, ByStorageTierFriendlyName, ByStorageTier,

ByVirtualDiskUniqueId, ByVirtualDiskName, ByVirtualDiskFriendlyName,

ByVirtualDisk

Aliases None

Dynamic? false

-StorageTier <CimInstance#MSFT_StorageTier>

Required? true

Position? 0

Accept pipeline input? true (ByValue)

Parameter set name ByStorageTier

Aliases None

Dynamic? false

-StorageTierFriendlyName <string>

Required? true
Position? Named
Accept pipeline input? false
Parameter set name ByStorageTierFriendlyName
Aliases None
Dynamic? false

-StorageTierUniqueld <string>

Required? true
Position? Named
Accept pipeline input? false
Parameter set name ByStorageTierUniqueld
Aliases None
Dynamic? false

-ThrottleLimit <int>

Required? false
Position? Named
Accept pipeline input? false
Parameter set name (All)
Aliases None
Dynamic? false

-VirtualDisk <CimInstance#MSFT_VirtualDisk>

Required? true
Position? 0
Accept pipeline input? true (ByValue)
Parameter set name ByVirtualDisk
Aliases None

Dynamic? false

-VirtualDiskFriendlyName <string>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByVirtualDiskFriendlyName

Aliases None

Dynamic? false

-VirtualDiskName <string>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByVirtualDiskName

Aliases None

Dynamic? false

-VirtualDiskUniqueld <string>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByVirtualDiskUniqueld

Aliases None

Dynamic? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Management.Infrastructure.CimInstance

OUTPUTS

System.Object

ALIASES

None

REMARKS

Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.

-- To download and install Help files for the module that includes this cmdlet, use Update-Help.