



Windows PowerShell Get-Help on Cmdlet 'Set-AzAdvisorConfiguration'

PS:\>Get-HELP Set-AzAdvisorConfiguration -Full

NAME

Set-AzAdvisorConfiguration

SYNOPSIS

Updates or creates the Azure Advisor Configuration.

SYNTAX

```
Set-AzAdvisorConfiguration [-SubscriptionId <String>] [-Exclude] [-LowCpuThreshold <CpuThreshold>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
    [<CommonParameters>]
```

```
Set-AzAdvisorConfiguration [-SubscriptionId <String>] -ResourceGroupName <String> [-Exclude] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
    [<CommonParameters>]
```

```

Set-AzAdvisorConfiguration -InputObject <IAdvisorIdentity> [-Exclude] [-LowCpuThreshold <CpuThreshold>]
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
[<CommonParameters>]

```

DESCRIPTION

Updates or creates the Azure Advisor Configuration.

PARAMETERS

-SubscriptionId <String>

The Azure subscription ID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the Azure resource group.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IAdvisorIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true
Position? named
Default value
Accept pipeline input? true (ByValue)
Accept wildcard characters? false

-Exclude [<SwitchParameter>]

Exclude the resource from Advisor evaluations.
Valid values: False (default) or True.

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-LowCpuThreshold <CpuThreshold>

Minimum percentage threshold for Advisor low CPU utilization evaluation.
Valid only for subscriptions.
Valid values: 5 (default), 10, 15 or 20.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Advisor.Models.IAdvisorIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Advisor.Models.Api202001.IConfigData

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

[about_Hash_Tables](#).

INPUTOBJECT <IAdvisorIdentity>: Identity Parameter

[ConfigurationName <ConfigurationName?>]: Advisor configuration name. Value must be 'default'

[Id <String>]: Resource identity path

[Name <String>]: Name of metadata entity.

[OperationId <String>]: The operation ID, which can be found from the Location field in the generate recommendation response header.

[RecommendationId <String>]: The recommendation ID.

[ResourceGroup <String>]: The name of the Azure resource group.

[ResourceUri <String>]: The fully qualified Azure Resource Manager identifier of the resource to which the recommendation applies.

[SubscriptionId <String>]: The Azure subscription ID.

----- EXAMPLE 1 -----

```
PS C:\>Set-AzAdvisorConfiguration -Exclude -LowCpuThreshold 20
```

----- EXAMPLE 2 -----

```
PS C:\>Set-AzAdvisorConfiguration -Exclude
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.advisor/Set-AzAdvisorConfiguration>

