



Windows PowerShell Get-Help on Cmdlet 'Set-AzApiManagementTenantAccess'

PS:\>Get-HELP Set-AzApiManagementTenantAccess -Full

NAME

Set-AzApiManagementTenantAccess

SYNOPSIS

Enables or disables tenant access.

SYNTAX

```

Set-AzApiManagementTenantAccess -Context
<Microsoft.Azure.Commands.ApiManagement.ServiceManagement.Models.PsApiManagementContext> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Enabled
<System.Boolean> [-PassThru] [<CommonParameters>]
  
```

DESCRIPTION

The Set-AzApiManagementTenantAccess cmdlet enables or disables tenant access.

PARAMETERS

-Context <Microsoft.Azure.Commands.ApiManagement.ServiceManagement.Models.PsApiManagementContext>

Specifies a PsApiManagementContext object.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Enabled <System.Boolean>

Specifies whether this cmdlet enables or disables tenant access. Specify a value of \$True to enable or \$False to disable.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-PassThru <System.Management.Automation.SwitchParameter>

Indicates that this cmdlet returns the PsApiManagementAccessInformation that this cmdlet modifies.

Required?	false
Position?	named
Default value	False

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.ApiManagement.ServiceManagement.Models.PsApiManagementContext

System.Management.Automation.SwitchParameter

OUTPUTS

Microsoft.Azure.Commands.ApiManagement.ServiceManagement.Models.PsApiManagementAccessInformation

NOTES

----- Example 1: Enable tenant access -----

```
$apimContext = New-AzApiManagementContext -ResourceGroupName "Api-Default-WestUS" -ServiceName "contoso"
Set-AzApiManagementTenantAccess -Context $apimContext -Enabled $True
```

This command enables tenant access in the specified context.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.apimanagement/set-azapimanagementtenantaccess>

Get-AzApiManagementTenantAccess