



Windows PowerShell Get-Help on Cmdlet 'Set-AzAutomationCertificate'

PS:\>Get-HELP Set-AzAutomationCertificate -Full

NAME

Set-AzAutomationCertificate

SYNOPSIS

Modifies the configuration of an Automation certificate.

SYNTAX

```
Set-AzAutomationCertificate [-ResourceGroupName] <System.String> [-AutomationAccountName] <System.String>
[-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Description
    <System.String>] [-Exportable
    <System.Nullable`1[System.Boolean]>] [-Password <System.Security.SecureString>] [-Path <System.String>]
[<CommonParameters>]
```

DESCRIPTION

The Set-AzAutomationCertificate cmdlet modifies the configuration of a certificate in Azure Automation.

PARAMETERS

-AutomationAccountName <System.String>

Specifies the name of the Automation account for which this cmdlet modifies a certificate.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Description <System.String>

Specifies a description for the certificate that this cmdlet modifies.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Exportable <System.Nullable`1[System.Boolean]>

Specifies whether the certificate can be exported.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the certificate that this cmdlet modifies.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Password <System.Security.SecureString>

Specifies the password for the certificate file.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Path <System.String>

Specifies the path to a script file to upload. The file can be a .cer file or a .pfx file.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group for which this cmdlet modifies a certificate.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

System.Security.SecureString

System.Nullable`1[[System.Boolean, System.Private.CoreLib, Version=4.0.0.0, Culture=neutral, PublicKeyToken=7cec85d7bea7798e]]

OUTPUTS

Microsoft.Azure.Commands.Automation.Model.CertificateInfo

NOTES

----- Example 1: Modify a certificate -----

```
$Password = ConvertTo-SecureString -String "Password" -AsPlainText -Force
```

```
Set-AzAutomationCertificate -AutomationAccountName "Contos17" -Name "ContosoCertificate" -Path "./cert.pfx"  
-Password $Password -ResourceGroupName "ResourceGroup01"
```

The first command converts a plain text password to be a secure string by using the ConvertTo-SecureString cmdlet. The command stores that object in the \$Password

variable. The second command modifies a certificate named ContosoCertificate. The command uses the password stored in \$Password. The command specifies the account name and the path of the file that it uploads.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/set-azautomationcertificate>

Get-AzAutomationCertificate

New-AzAutomationCertificate

Remove-AzAutomationCertificate