



Windows PowerShell Get-Help on Cmdlet 'Set-AzCurrentStorageAccount'

PS:\>Get-HELP Set-AzCurrentStorageAccount -Full

NAME

Set-AzCurrentStorageAccount

SYNOPSIS

Modifies the current Storage account of the specified subscription.

SYNTAX

```
Set-AzCurrentStorageAccount -Context
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Set-AzCurrentStorageAccount [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name <System.String>

-ResourceGroupName <System.String> [<CommonParameters>]
```

The Set-AzCurrentStorageAccount cmdlet modifies the current Azure Storage account of the specified Azure subscription in Azure PowerShell. The current Storage account is used as the default when you access Storage without specifying a Storage account name.

PARAMETERS

-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>

Specifies an AzureStorageContext object for the current Storage account. To obtain a storage context object, use the New-AzStorageContext cmdlet.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of the Storage account that this cmdlet modifies.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-ResourceGroupName <System.String>

Specifies the resource group that contains the Storage account to modify.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext

System.String

OUTPUTS

System.String

NOTES

----- Example 1: Set the current Storage account -----

```
Set-AzCurrentStorageAccount -ResourceGroupName "RG01" -Name "mystorageaccount"
```

This command sets the default Storage account for the specified subscription.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/set-azcurrentstorageaccount>

Set-AzStorageAccount