



Windows PowerShell Get-Help on Cmdlet 'Set-AzDataLakeAnalyticsDataSource'

PS:\>Get-HELP Set-AzDataLakeAnalyticsDataSource -Full

NAME

Set-AzDataLakeAnalyticsDataSource

SYNOPSIS

Modifies the details of a data source of a Data Lake Analytics account.

SYNTAX

```
Set-AzDataLakeAnalyticsDataSource [-Account] <System.String> [-Blob] <System.String> [-AccessKey] <System.String>
[[-ResourceGroupName] <System.String>]
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

The Set-AzDataLakeAnalyticsDataSource cmdlet modifies the details of a data source of an Azure Data Lake Analytics account.

-AccessKey <System.String>

Specifies the new access key of the Azure Blob Storage data source.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Account <System.String>

Specifies the Data Lake Analytics account name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Blob <System.String>

Specifies the name of the Azure Blob Storage data source.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the resource group name of the Data Lake Analytics account.

Required? false

Position? 3

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Void

NOTES

----- Example 1: Change the access key for a data source -----

```
Set-AzDataLakeAnalyticsDataSource -Account "ContosoAdlAccount" -Blob "contosowasb" -AccessKey  
"...newaccesskey..."
```

This command changes the access key stored for an Azure Blob Storage data source.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datalakeanalytics/set-azdatalakeanalyticsdatasource>

Add-AzDataLakeAnalyticsDataSource

Remove-AzDataLakeAnalyticsDataSource