



Windows PowerShell Get-Help on Cmdlet 'Set-AzDefault'

PS:\>Get-HELP Set-AzDefault -Full

NAME

Set-AzDefault

SYNOPSIS

Sets a default in the current context

SYNTAX

```

Set-AzDefault [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]
[-ResourceGroupName
<System.String>] [-Scope {Process | CurrentUser}] [-Confirm] [-WhatIf] [<CommonParameters>]

```

DESCRIPTION

The Set-AzDefault cmdlet adds or changes the defaults in the current context.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Create a new resource group if specified default does not exist

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of the resource group being set as default

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Scope <Microsoft.Azure.Commands.Profile.Common.ContextModificationScope>

Determines the scope of context changes, for example, whether changes apply only to the current process, or to all sessions started by this user.

Required? false
Position? named
Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

NOTES

----- Example 1 -----

Set-AzDefault -ResourceGroupName myResourceGroup

Id : /subscriptions/xxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxx/resourceGroups/myResourceGroup

Name : myResourceGroup

Properties : Microsoft.Azure.Management.Internal.Resources.Models.ResourceGroupProperties

Location : eastus

ManagedBy :

Tags :

This command sets the default resource group to the resource group specified by the user.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/set-azdefault>