



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Set-AzEventHubGeoDRConfigurationBreakPair'

PS:\>Get-HELP Set-AzEventHubGeoDRConfigurationBreakPair -Full

NAME

Set-AzEventHubGeoDRConfigurationBreakPair

SYNOPSIS

This operation disables the Disaster Recovery and stops replicating changes from primary to secondary namespaces

SYNTAX

```
Set-AzEventHubGeoDRConfigurationBreakPair -Name <String> -NamespaceName <String> -ResourceGroupName  
<String> [-SubscriptionId <String>] [-DefaultProfile <PSObject>]  
[-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait]  
[-Proxy <Uri>] [-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
Set-AzEventHubGeoDRConfigurationBreakPair -InputObject <IEventHubIdentity> [-DefaultProfile <PSObject>] [-AsJob]  
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>]  
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

DESCRIPTION

This operation disables the Disaster Recovery and stops replicating changes from primary to secondary namespaces

PARAMETERS

-Name <String>

The name of the Consumer Group.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NamespaceName <String>

The name of EventHub namespace

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IEventHubIdentity>

Identity parameter.

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.EventHub.Models.IEventHubIdentity

OUTPUTS

System.Boolean

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help about_Hash_Tables.

INPUTOBJECT <IEventHubIdentity>: Identity parameter. To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

[Alias <String>]: The Disaster Recovery configuration name

[ApplicationGroupName <String>]: The Application Group name

[AuthorizationRuleName <String>]: The authorization rule name.

[ClusterName <String>]: The name of the Event Hubs Cluster.

[ConsumerGroupName <String>]: The consumer group name

[EventHubName <String>]: The Event Hub name

[Id <String>]: Resource identity path

[NamespaceName <String>]: The Namespace name

[PrivateEndpointConnectionName <String>]: The PrivateEndpointConnection name

[ResourceAssociationName <String>]: The ResourceAssociation Name

[ResourceGroupName <String>]: Name of the resource group within the azure subscription.

[SchemaGroupName <String>]: The Schema Group name

[SubscriptionId <String>]: Subscription credentials that uniquely identify a Microsoft Azure subscription. The subscription ID forms part of the URI for every service call.

----- EXAMPLE 1 -----

```
PS C:\>Set-AzEventHubGeoDRConfigurationBreakPair -ResourceGroupName myResourceGroup -NamespaceName myPrimaryNamespace -Name myAlias
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.eventhub/set-azeventhubgeodrconfigurationbreakpair>