



Windows PowerShell Get-Help on Cmdlet 'Set-AzTrafficManagerProfile'

PS:\>Get-HELP Set-AzTrafficManagerProfile -Full

NAME

Set-AzTrafficManagerProfile

SYNOPSIS

Updates a Traffic Manager profile.

SYNTAX

```
Set-AzTrafficManagerProfile [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -TrafficManagerProfile  
<Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile> [<CommonParameters>]
```

DESCRIPTION

The Set-AzTrafficManagerProfile cmdlet updates an Azure Traffic Manager profile. This cmdlet updates the settings of the profile from a local profile object. You can

specify the profile object either by using the TrafficManagerProfile parameter or by using the pipeline.

You can obtain a local object that represents a profile by using the Get-AzTrafficManagerProfile cmdlet. Modify the object locally and then use

Set-AzTrafficManagerProfile to commit your changes.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-TrafficManagerProfile <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile>

Specifies a local TrafficManagerProfile object. This cmdlet updates Traffic Manager to match this local object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

OUTPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

NOTES

----- Example 1: Update a profile -----

```
$TrafficManagerProfile = Get-AzTrafficManagerProfile -Name "ContosoProfile" -ResourceGroupName  
"ResourceGroup11"  
$TrafficManagerProfile.ProfileStatus = "Disabled"  
Set-AzTrafficManagerProfile -TrafficManagerProfile $TrafficManagerProfile
```

The first command gets an Azure Traffic Manager profile by using the Get-AzTrafficManagerProfile cmdlet. The command stores the profile locally in the

\$TrafficManagerProfile variable.

The second command changes that profile locally. This command disables the profile.

The third command updates the Traffic Manager profile named ContosoProfile to match the local value in \$TrafficManagerProfile.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.trafficmanager/set-aztrafficmanagerprofile>

Add-AzTrafficManagerEndpointConfig

Get-AzTrafficManagerProfile

New-AzTrafficManagerProfile

Remove-AzTrafficManagerEndpointConfig

Remove-AzTrafficManagerProfile