



Windows PowerShell Get-Help on Cmdlet 'Set-AzVirtualNetworkGatewayConnectionSharedKey'

PS:\>Get-HELP Set-AzVirtualNetworkGatewayConnectionSharedKey -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Set-AzVirtualNetworkGatewayConnectionSharedKey

SYNOPSIS

Configures the shared key of the virtual network gateway connection.

SYNTAX

```

Set-AzVirtualNetworkGatewayConnectionSharedKey [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]
-Name <System.String> -ResourceGroupName <System.String> -Value <System.String> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

DESCRIPTION

The Set-AzVirtualNetworkGatewayConnectionSharedKey cmdlet configures the shared key of the virtual network gateway connection.

gateway connection.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the virtual network gateway shared key.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group that the virtual network gateway belongs to

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Value <System.String>

Specifies the value of the shared key.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.String

NOTES

----- Example 1 -----

```
Set-AzVirtualNetworkGatewayConnectionSharedKey -ResourceGroupName VPNGatewayV3 -Name VNet1toVNet2  
-Value abcd1234
```

Confirm

Are you sure you want to overwrite resource 'VNet1toVNet2'

[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"): y

abcd1234

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/set-azvirtualnetworkgatewayconnectionsharedkey>

Get-AzVirtualNetworkGatewayConnectionSharedKey

Reset-AzVirtualNetworkGatewayConnectionSharedKey