



Windows PowerShell Get-Help on Cmdlet 'Set-BcdBootDisplayOrder'

PS:\>Get-HELP Set-BcdBootDisplayOrder -Full

NAME

Set-BcdBootDisplayOrder

SYNTAX

Set-BcdBootDisplayOrder [-Id] <string[]> [[-Store] <BcdStoreInfo>] -AddFirst [-Force] [-WhatIf] [-Confirm]

[<CommonParameters>]

Set-BcdBootDisplayOrder [-Entry] <BcdEntryInfo[]> -AddFirst [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdBootDisplayOrder [-Id] <string[]> [[-Store] <BcdStoreInfo>] -AddLast [-Force] [-WhatIf] [-Confirm]

[<CommonParameters>]

Set-BcdBootDisplayOrder [-Entry] <BcdEntryInfo[]> -AddLast [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdBootDisplayOrder [-Id] <string[]> [[-Store] <BcdStoreInfo>] -Remove [-Force] [-WhatIf] [-Confirm]

[<CommonParameters>]

Set-BcdBootDisplayOrder [-Entry] <BcdEntryInfo[]> -Remove [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdBootDisplayOrder [-Id] <string[]> [[-Store] <BcdStoreInfo>] [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdBootDisplayOrder [-Entry] <BcdEntryInfo[]> [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

PARAMETERS

-AddFirst

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	AddFirstId, AddFirstEntry
Aliases	None
Dynamic?	false

-AddLast

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	AddLastId, AddLastEntry
Aliases	None
Dynamic?	false

-Confirm

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	cf
Dynamic?	false

-Entry <BcdEntryInfo[]>

Required?	true
Position?	0
Accept pipeline input?	true (ByValue)
Parameter set name	AddFirstEntry, AddLastEntry, RemoveEntry, ReplaceEntry
Aliases	None
Dynamic?	false

-Force

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-Id <string[]>

Required?	true
Position?	0
Accept pipeline input?	true (ByValue, ByPropertyName)
Parameter set name	AddFirstId, AddLastId, RemoveId, ReplaceId
Aliases	Identifier
Dynamic?	false

-Remove

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	RemoveId, RemoveEntry
Aliases	None

Dynamic? false

-Store <BcdStoreInfo>

Required? false

Position? 1

Accept pipeline input? false

Parameter set name AddFirstId, AddLastId, RemoveId, ReplaceId

Aliases None

Dynamic? false

-WhatIf

Required? false

Position? Named

Accept pipeline input? false

Parameter set name (All)

Aliases wi

Dynamic? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String[]

Microsoft.Windows.Bcd.Cmdlets.BcdExtensions.BcdEntryInfo[]

OUTPUTS

System.Object

ALIASES

None

REMARKS

None