



Windows PowerShell Get-Help on Cmdlet 'Start-AzRecoveryServicesAsrCancelFailoverJob'

PS:\>Get-HELP Start-AzRecoveryServicesAsrCancelFailoverJob -Full

NAME

Start-AzRecoveryServicesAsrCancelFailoverJob

SYNOPSIS

Starts the cancel failover action for a Site Recovery object.

SYNTAX

```
Start-AzRecoveryServicesAsrCancelFailoverJob [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -RecoveryPlan  
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan> [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

```
Start-AzRecoveryServicesAsrCancelFailoverJob [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]  
    -ReplicationProtectedItem <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRReplicationProtectedItem>  
[-Confirm] [-WhatIf] [<CommonParameters>]
```

The Start-AzRecoveryServicesAsrCancelFailoverJob cmdlet starts the cancel failover process for an Azure Site Recovery object.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RecoveryPlan <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan>

Specifies an ASR recovery plan object corresponding to recovery plan to be failovered.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ReplicationProtectedItem <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRReplicationProtectedItem>

Specifies an ASR replication protected item object corresponding to replication protected item to be failovered.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRReplicationProtectedItem

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1 -----

```
$currentJob = Start-AzRecoveryServicesAsrCancelFailoverJob -RecoveryPlan $RP
```

Starts the cancel failover for the specified recovery plan and returns the ASR job used to track the operation.

----- Example 2 -----

```
Start-AzRecoveryServicesAsrCancelFailoverJob -ReplicationProtectedItem $ReplicationProtectedItem
```

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/start-azrecoveryservicesasrcancelfailoverjob>