



Windows PowerShell Get-Help on Cmdlet 'Start-AzServiceBusMigration'

PS:\>Get-HELP Start-AzServiceBusMigration -Full

NAME

Start-AzServiceBusMigration

SYNOPSIS

Create Migration configuration and starts migration of entities from Standard to Premium namespace

SYNTAX

```
Start-AzServiceBusMigration -NamespaceName <String> -ResourceGroupName <String> [-SubscriptionId <String>]
[-PostMigrationName <String>] [-TargetNamespace <String>]
[-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Create Migration configuration and starts migration of entities from Standard to Premium namespace

-NamespaceName <String>

The namespace name

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the Resource group within the Azure subscription.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

Subscription credentials that uniquely identify a Microsoft Azure subscription.

The subscription ID forms part of the URI for every service call.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PostMigrationName <String>

Name to access Standard Namespace after migration

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-TargetNamespace <String>

Existing premium Namespace ARM Id name which has no entities, will be used for migration

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ServiceBus.Models.IMigrationConfigProperties

----- EXAMPLE 1 -----

```
PS C:\>Start-AzServiceBusMigration -ResourceGroupName myResourceGroup -NamespaceName myNamespace  
-PostMigrationName myStandardNamespace2 -TargetNamespace
```

```
/subscriptions/subscriptionId/resourceGroups/myResourceGroup/providers/Microsoft.ServiceBus/namespaces/myPremium  
Namespace
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.servicebus/start-azservicebusmigration>