



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Stop-AzDataFactoryV2TriggerRun'***

**PS:\>Get-HELP Stop-AzDataFactoryV2TriggerRun -Full**

#### **NAME**

Stop-AzDataFactoryV2TriggerRun

#### **SYNOPSIS**

Stops a trigger run in a data factory.

#### **SYNTAX**

```
Stop-AzDataFactoryV2TriggerRun [-DataFactory] <Microsoft.Azure.Commands.DataFactoryV2.Models.PSDataFactory>
[-TriggerName] <System.String> [-TriggerRunId]
                                     <System.String>           [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru] [-Confirm]
[-WhatIf]
[<CommonParameters>]
```

```
Stop-AzDataFactoryV2TriggerRun [-ResourceGroupName] <System.String> [-DataFactoryName] <System.String>
[-TriggerName] <System.String> [-TriggerRunId] <System.String>
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Stop-AzDataFactoryV2TriggerRun [-InputObject] <Microsoft.Azure.Commands.DataFactoryV2.Models.PSTriggerRun>
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

## DESCRIPTION

The Stop-AzDataFactoryV2TriggerRun cmdlet stops a trigger run in a data factory specified with the trigger name and trigger run ID. Currently only supported for TumblingWindowTriggers in WaitingOnDependency State.

## PARAMETERS

**-DataFactory** <Microsoft.Azure.Commands.DataFactoryV2.Models.PSDataFactory>

The data factory object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

**-DataFactoryName** <System.String>

The data factory name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

**-DefaultProfile** <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.DataFactoryV2.Models.PSTriggerRun>

The information about the trigger run.

Required? true  
Position? 0  
Default value None  
Accept pipeline input? True (ByValue)  
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

If specified the cmdlet write true in case operation succeeds.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true  
Position? 0  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

-TriggerName <System.String>

The trigger name.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-TriggerRunId <System.String>

The Run ID of the trigger.

Required? true

Position? 3

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value              False

Accept pipeline input?    False

Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

#### INPUTS

Microsoft.Azure.Commands.DataFactoryV2.Models.PSTriggerRun

System.String

Microsoft.Azure.Commands.DataFactoryV2.Models.PSDataFactory

#### OUTPUTS

System.Boolean

#### NOTES

----- Example 1 -----

```
Stop-AzDataFactoryV2TriggerRun -ResourceGroupName "ADF" -DataFactoryName "WikiADF" -TriggerName  
"testTumblingWindowTrigger" -TriggerRunId  
08586002468005888497807248799CU16
```

This command stops the trigger run with id '08586002468005888497807248799CU16' in the factory WikiADF.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datafactory/stop-azdatafactoryv2triggerrun>