



Windows PowerShell Get-Help on Cmdlet 'Stop-AzRecoveryServicesBackupJob'

PS: \>Get-HELP Stop-AzRecoveryServicesBackupJob -Full

NAME

Stop-AzRecoveryServicesBackupJob

SYNOPSIS

Cancels a running job.

SYNTAX

```

Stop-AzRecoveryServicesBackupJob [-Job]
<Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.JobBase> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-VaultId
<System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]

Stop-AzRecoveryServicesBackupJob [-JobId] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-VaultId <System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Stop-AzRecoveryServicesBackupJob cmdlet cancels an existing Azure Backup job. Use this cmdlet to stop a job that

takes too long and blocks other activities. You

can cancel only Backup and Restore job types. Set the vault context by using the `Set-AzRecoveryServicesVaultContext` cmdlet before you use the current cmdlet.

PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-Job <Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.JobBase>`

Specifies a job that this cmdlet cancels. To obtain a `BackupJob` object, use the `Get-AzRecoveryServicesBackupJob` cmdlet.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-JobId <System.String>`

Specifies the ID of the job to cancel. The ID is the `InstanceId` property of a `BackupJob` object. To obtain an `BackupJob` object, use `Get-AzRecoveryServicesBackupJob`.

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-VaultId <System.String>

ARM ID of the Recovery Services Vault.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.JobBase

NOTES

----- Example 1: Stop a backup job -----

```
$Job = Get-AzRecoveryServicesBackupJob -Operation Backup
```

```
Stop-AzRecoveryServicesBackupJob -JobID $Job.InstanceId
```

The first command gets a backup job, and then stores the job in the \$Job variable. The last command stops the job by specifying the Instance ID of the backup job in

```
$Job.
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.recoveryservices/stop-azrecoveryservicesbackupjob>

Get-AzRecoveryServicesBackupJob

Wait-AzRecoveryServicesBackupJob

