



Windows PowerShell Get-Help on Cmdlet 'Unregister-AzAutomationDscNode'

PS:\>Get-HELP Unregister-AzAutomationDscNode -Full

NAME

Unregister-AzAutomationDscNode

SYNOPSIS

Removes a DSC node from management by an Automation account.

SYNTAX

```
Unregister-AzAutomationDscNode [-ResourceGroupName] <System.String> [-AutomationAccountName]
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Id
<System.Guid> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Unregister-AzAutomationDscNode cmdlet removes an APS Desired State Configuration (DSC) node from management by an Azure Automation account.

-AutomationAccountName <System.String>

Specifies the name of the Automation account from which this cmdlet removes a DSC node.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

ps_force

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Id <System.Guid>

Specifies the unique ID of the DSC node that this cmdlet removes.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group in which this cmdlet unregisters a DSC node.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.Guid

System.String

OUTPUTS

Microsoft.Azure.Commands.Automation.Model.DscNode

NOTES

Example 1: Remove an Azure DSC node from management by an Automation account

```
Unregister-AzAutomationDscNode -AutomationAccountName "Contoso17" -ResourceGroupName "ResourceGroup01" -Id 064a8929-c98b-25e4-80hh-111ca86067j8
```

This command removes the DSC node that has the specified GUID from management by the Automation account named Contoso17.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/unregister-azautomationdscnode>

Get-AzAutomationDscNode

Register-AzAutomationDscNode

Set-AzAutomationDscNode