



Windows PowerShell Get-Help on Cmdlet 'Unregister-AzStorageSyncServer'

PS:\>Get-HELP Unregister-AzStorageSyncServer -Full

NAME

Unregister-AzStorageSyncServer

SYNOPSIS

Warning: Unregistering a server will result in cascading deletes of all server endpoints on this server. This command will unregister a server from it's storage sync service.

SYNTAX

```
Unregister-AzStorageSyncServer [-InputObject] <Microsoft.Azure.Commands.StorageSync.Models.PSRegisteredServer>
[-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Unregister-AzStorageSyncServer [-ResourceGroupName] <System.String> [-StorageSyncServiceName]
<System.String> [-ServerId] <System.Guid> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

Unregister-AzStorageSyncServer [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

This command will unregister a server from the storage sync service. Warning: Unregistering a server will result in cascading deletes of all server endpoints on this server. It should only be called when you are certain that no path on this server is to be synced anymore.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Supply -Force to skip confirmation of this command.

Required? false
Position? named
Default value False
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.StorageSync.Models.PSRegisteredServer>

RegisteredServer Input Object, normally passed through the pipeline.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

In normal execution, this cmdlet returns no value on success. If you provide the PassThru parameter, then the cmdlet will write a value to the pipeline after successful execution.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name.

Required? true
Position? 0
Default value None
Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

RegisteredServer Resource Id

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerId <System.Guid>

Name of the RegisteredServer.

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-StorageSyncServiceName <System.String>

Name of theStorageSyncService.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts for confirmation before running the cmdlet.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.StorageSync.Models.PSRegisteredServer

System.String

System.Management.Automation.SwitchParameter

OUTPUTS

System.Object

NOTES

----- Example 1 -----

```
$RegisteredServer = Get-AzStorageSyncServer -ResourceGroupName "myResourceGroup" -StorageSyncServiceName  
"myStorageSyncServiceName"  
  
Unregister-AzStorageSyncServer -Force -ResourceGroupName "myResourceGroup" -StorageSyncServiceName  
"myStorageSyncServiceName" -ServerId $RegisteredServer.ServerId
```

This command will unregister the server, causing cascading deletes of all server endpoints on this server.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/Az.storage-sync/unregister-AzStorageSyncServer>