



Windows PowerShell Get-Help on Cmdlet 'Update-AzArcResourceBridge'

PS:\>Get-HELP Update-AzArcResourceBridge -Full

NAME

Update-AzArcResourceBridge

SYNOPSIS

Updates an Appliance with the specified Resource Name in the specified Resource Group and Subscription.

SYNTAX

Update-AzArcResourceBridge -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] [-Tag <Hashtable>] [-DefaultProfile <PSObject>] [-Break]

[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]

[-WhatIf] [-Confirm] [<CommonParameters>]

Update-AzArcResourceBridge -InputObject <IArcResourceBridgeIdentity> [-Tag <Hashtable>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]

[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

Updates an Appliance with the specified Resource Name in the specified Resource Group and Subscription.

PARAMETERS

-Name <String>

Appliances name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IArcResourceBridgeIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-Tag <Hashtable>

Resource tags

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.ArcResourceBridge.Models.IArcResourceBridgeIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ArcResourceBridge.Models.Api20221027.IAppliance

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help [about_Hash_Tables](#).

INPUTOBJECT <IArcResourceBridgeIdentity>: Identity Parameter

[Id <String>]: Resource identity path

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[ResourceName <String>]: Appliances name.

[SubscriptionId <String>]: The ID of the target subscription.

[UpgradeGraph <String>]: Upgrade graph version, ex - stable

----- EXAMPLE 1 -----

PS C:\>Update-AzArcResourceBridge -Name azps-resource-bridge -ResourceGroupName azps_test_group -Tag

```
@{"111"="222";"aaa"="bbb"}
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzArcResourceBridge -ResourceGroupName azps_test_group -Name azps-resource-bridge |  
Update-AzArcResourceBridge -Tag @{"111"="222";"aaa"="bbb"}
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.arcresourcebridge/update-azarcresourcebridge>