



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### **Windows PowerShell Get-Help on Cmdlet 'Update-AzCosmosDBGremlinDatabase'**

**PS:\>Get-HELP Update-AzCosmosDBGremlinDatabase -Full**

#### **NAME**

Update-AzCosmosDBGremlinDatabase

#### **SYNOPSIS**

Updates the CosmosDB Gremlin Database. Performs a client side patch operation by reading the existing Database.

#### **SYNTAX**

```
Update-AzCosmosDBGremlinDatabase      -AccountName      <System.String>      [-AutoscaleMaxThroughput  
<System.Nullable`1[System.Int32]>] [-DefaultProfile  
                                     <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]      [-Name  
<System.String>] -ResourceGroupName <System.String> [-Throughput  
                                     <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Update-AzCosmosDBGremlinDatabase [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>] [-DefaultProfile  
                                     <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject  
                                     <Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults>      [-Name      <System.String>]  
[-Throughput <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

```
Update-AzCosmosDBGremlinDatabase [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>] [-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name <System.String>] -ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> [-Throughput <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

## DESCRIPTION

Updates the CosmosDB Gremlin Database. Performs a client side patch operation by reading the existing Database.

## PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>

Maximum Throughput value if autoscale is enabled.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults>

Gremlin Database object.

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByValue)  
Accept wildcard characters? false

-Name <System.String>

Database name.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByValue)  
Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Throughput <System.Nullable`1[System.Int32]>

The throughput of Gremlin Database (RU/s). Default value is 400.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

#### INPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccount

Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults

#### OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults

Microsoft.Azure.Commands.CosmosDB.Exceptions.ResourceNotFoundException

#### NOTES

----- Example 1 -----

-ResourceGroupName "myResourcegroupName" -Throughput 700

Name : myDatabaseName

Id :

/subscriptions/mySubscriptionId/resourceGroups/myResourcegroupName/providers/Microsoft.DocumentDB/databaseAccounts/myAccountName/gremlinDatabases/myDatabaseName

Location :

Tags :

Resource : Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetPropertiesResource

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/update-azcosmosdbgremlindatabase>