



Windows PowerShell Get-Help on Cmdlet 'Update-AzCosmosDBGremlinDatabaseThroughput'

PS:\>Get-HELP Update-AzCosmosDBGremlinDatabaseThroughput -Full

NAME

Update-AzCosmosDBGremlinDatabaseThroughput

SYNOPSIS

Updates the throughput value of a CosmosDB Gremlin Database.

SYNTAX

```
Update-AzCosmosDBGremlinDatabaseThroughput -AccountName <System.String> [-AutoscaleMaxThroughput
<System.Nullable`1[System.Int32]>] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] -ResourceGroupName <System.String> [-Throughput
<System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Update-AzCosmosDBGremlinDatabaseThroughput [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>]
[-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults> [-Name <System.String>]
[-Throughput <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

Update-AzCosmosDBGremlinDatabaseThroughput [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>]
 [-DefaultProfile
 <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
 <System.String>] -ParentObject
 <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> [-Throughput
 <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Updates the throughput value of a CosmosDB Gremlin Database.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>

Maximum Throughput value if autoscale is enabled.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSGremlinDatabaseGetResults>

CosmosDB Account object

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <System.String>

Database name.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Throughput <System.Nullable`1[System.Int32]>

The throughput of Gremlin Database (RU/s). Default value is 400.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccount

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSThroughputSettingsGetResults

NOTES

----- Example 1 -----

```
Update-AzCosmosDBGremlinDatabaseThroughput -AccountName "myAccountName" -ResourceGroupName  
"myResourceGroupName" -Name "myDatabaseName" -Throughput  
$updatedThroughputValue
```

Id

:

/subscriptions/{mySubscriptionId}/resourceGroups/{myResourceGroupName}/providers/Microsoft.DocumentDB/databaseAccounts/{myAccountName}/gremlinDat

abases/{myDatabaseName}/throughputSettings/default

Throughput : {updatedThroughputValue}

MinimumThroughput : 400

OfferReplacePending :

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.cosmosdb/update-azcosmosdbgremlindatabasethroughput>