



Windows PowerShell Get-Help on Cmdlet 'Update-AzDatabricksAccessConnector'

PS:\>Get-HELP Update-AzDatabricksAccessConnector -Full

NAME

Update-AzDatabricksAccessConnector

SYNOPSIS

Updates an azure databricks accessConnector.

SYNTAX

```
Update-AzDatabricksAccessConnector -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>]
[-IdentityType <ManagedServiceIdentityType>]
[-IdentityUserAssignedIdentity <Hashtable>] [-Tag <Hashtable>] [-DefaultProfile <PSObject>] [-AsJob] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

```
Update-AzDatabricksAccessConnector -InputObject <IDatabricksIdentity> [-IdentityType <ManagedServiceIdentityType>]
[-IdentityUserAssignedIdentity <Hashtable>] [-Tag
<Hashtable>] [-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>]
```

[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

Updates an azure databricks accessConnector.

PARAMETERS

-Name <String>

The name of the azure databricks accessConnector.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IDatabricksIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-IdentityType <ManagedServiceIdentityType>

Type of managed service identity (where both SystemAssigned and UserAssigned types are allowed).

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-IdentityUserAssignedIdentities <Hashtable>

The set of user assigned identities associated with the resource.

The userAssignedIdentities dictionary keys will be ARM resource ids in the form:

/subscriptions/{subscriptionId}/resourceGroups/{resourceGroupName}/providers/Microsoft.ManagedIdentity/userAssignedIdentities/{identityName}.

The dictionary values can be empty objects ({} in requests.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Tag <Hashtable>

Resource tags.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Databricks.Models.IDatabricksIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Databricks.Models.Api20230501.IAccessConnector

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <IDatabricksIdentity>: Identity Parameter

[ConnectorName <String>]: The name of the azure databricks accessConnector.

[GroupId <String>]: The name of the private link resource

[Id <String>]: Resource identity path

[PeeringName <String>]: The name of the workspace vNet peering.

[PrivateEndpointConnectionName <String>]: The name of the private endpoint connection

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

[WorkspaceName <String>]: The name of the workspace.

----- EXAMPLE 1 -----

```
PS C:\>Update-AzDatabricksAccessConnector -ResourceGroupName azps_test_gp_db -Name  
azps-databricks-accessconnector -Tag @{key='value'}
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzDatabricksAccessConnector -ResourceGroupName azps_test_gp_db -Name  
azps-databricks-accessconnector | Update-AzDatabricksAccessConnector -Tag  
@{key='value'}
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.databricks/update-azdatabricksaccessconnector>