



Windows PowerShell Get-Help on Cmdlet 'Update-AzMaintenanceConfiguration'

PS:\>Get-HELP Update-AzMaintenanceConfiguration -Full

NAME

Update-AzMaintenanceConfiguration

SYNOPSIS

Patch configuration record

SYNTAX

Update-AzMaintenanceConfiguration [-ResourceGroupName] <System.String> [-Name] <System.String> [-Configuration]

<Microsoft.Azure.Commands.Maintenance.Models.PSMaintenanceConfiguration> [-AsJob] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]

[<CommonParameters>]

DESCRIPTION

Patch maintenance configuration record

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Configuration <Microsoft.Azure.Commands.Maintenance.Models.PSMaintenanceConfiguration>

The maintenance configuration to be updated.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The maintenance configuration Name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource Group Name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Maintenance.Models.PSMaintenanceConfiguration

OUTPUTS

Microsoft.Azure.Commands.Maintenance.Models.PSMaintenanceConfiguration

NOTES

----- Example 1 -----

```
Update-AzMaintenanceConfiguration -ResourceGroupName smdtest -Name workervmscentralus -Configuration  
$configuration
```

Location : centralus

Tags : {}

ExtensionProperties : {}

MaintenanceScope : Host

Id :

anceConfigurations/workervmscentralus

Name : workervmscentralus

Type : Microsoft.Maintenance/maintenanceConfigurations

Patch maintenance configuration record

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.maintenance/update-azmaintenanceconfiguration>