



## ***Windows PowerShell Get-Help on Cmdlet 'Update-AzRecoveryServicesAsrNetworkMapping'***

***PS:\>Get-HELP Update-AzRecoveryServicesAsrNetworkMapping -Full***

### NAME

Update-AzRecoveryServicesAsrNetworkMapping

### SYNOPSIS

Updates the specified azure site recovery network mapping.

### SYNTAX

```
Update-AzRecoveryServicesAsrNetworkMapping [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping> -RecoveryAzureNetworkId
<System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Update-AzRecoveryServicesAsrNetworkMapping [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping> -RecoveryNetwork
<Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetwork>
[-Confirm] [-WhatIf] [<CommonParameters>]
```

## DESCRIPTION

The `Update-AzRecoveryServicesAsrNetworkMapping` cmdlet updates the specified Azure Site Recovery network mapping.

## PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping>`

Input Object: Specifies the ASR network mapping object corresponding to the ASR network mapping to be updated.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

`-RecoveryAzureNetworkId <System.String>`

Specifies the recovery azure network ID for the network mapping.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RecoveryNetwork <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetwork>

Specifies the recovery network object for the network mapping.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRNetworkMapping

## OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

## NOTES

----- Example 1 -----

Update-AzRecoveryServicesAsrNetworkMapping -InputObject \$NetworkMapping -RecoveryNetwork \$RecoveryNetwork

Starts the update network mapping operation using the specified parameters and returns the ASR job used to track the operation.

## RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/update-azrecoveryservicesasrnetworkmapping>