



Windows PowerShell Get-Help on Cmdlet 'Update-AzRecoveryServicesAsrRecoveryPlan'

PS:\>Get-HELP Update-AzRecoveryServicesAsrRecoveryPlan -Full

NAME

Update-AzRecoveryServicesAsrRecoveryPlan

SYNOPSIS

Updates the contents of an Azure Site recovery plan.

SYNTAX

```

Update-AzRecoveryServicesAsrRecoveryPlan [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```

Update-AzRecoveryServicesAsrRecoveryPlan [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Path
    <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Update-AzRecoveryServicesAsrRecoveryPlan cmdlet updates the contents of a recovery plan using the contents of

the specified ASR recovery plan object or ASR
recovery plan definition json file.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan>

Input Object to the cmdlet: Specifies an ASR recovery plan object, the contents of which are used to update the recovery plan referred to by the object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Path <System.String>

Specifies the path of the recovery plan definition json file used to update the recovery plan.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRRecoveryPlan

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1: Update a recovery plan -----

```
$currentJob = Update-AzRecoveryServicesAsrRecoveryPlan -RecoveryPlan $RP
```

Start the operation of updating a recovery plan using the contents of the specified ASR recovery plan object and returns the ASR job used to track the operation.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/update-azrecoveryservicesasrrecoveryplan>

Get-AzRecoveryServicesAsrRecoveryPlan

New-AzRecoveryServicesAsrRecoveryPlan

Remove-AzRecoveryServicesAsrRecoveryPlan