



Windows PowerShell Get-Help on Cmdlet 'Update-AzSynapseLinkConnectionLandingZoneCredential'

PS:\>Get-HELP Update-AzSynapseLinkConnectionLandingZoneCredential -Full

NAME

Update-AzSynapseLinkConnectionLandingZoneCredential

SYNOPSIS

Updates the landing zone credential of a link connection.

SYNTAX

```

Update-AzSynapseLinkConnectionLandingZoneCredential [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource> -SasToken
<Azure.Analytics.Synapse.Artifacts.Models.SecureString> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Update-AzSynapseLinkConnectionLandingZoneCredential [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-LinkConnectionName <System.String> -SasToken <Azure.Analytics.Synapse.Artifacts.Models.SecureString>
-WorkspaceName <System.String> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

-LinkConnectionName <System.String> -SasToken <Azure.Analytics.Synapse.Artifacts.Models.SecureString>

-WorkspaceObject

<Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Update-AzSynapseLinkConnectionLandingZoneCredential cmdlet updates the landing zone credential of a link connection.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource>

The information about the link connection.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-LinkConnectionName <System.String>

Name of link connection.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-SasToken <Azure.Analytics.Synapse.Artifacts.Models.SecureString>

Landing zone's sas token.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

```
Update-AzSynapseLinkConnectionLandingZoneCredential -WorkspaceName ContosoWorkspace -LinkConnectionName  
ContosoLinkConnection -SasToken "SampleSasToken"
```

This command updates the landing zone credential with sas token "exampleSasToken" of link connection ContosoLinkConnection in workspace ContosoWorkspace.

----- Example 2 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace  
$ws | Update-AzSynapseLinkConnectionLandingZoneCredential -LinkConnectionName ContosoLinkConnection  
-SasToken "SampleSasToken"
```

This command updates the landing zone credential with sas token "exampleSasToken" of link connection ContosoLinkConnection in workspace ContosoWorkspace through pipeline.

----- Example 3 -----

```
$lc = Get-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

\$lc | Update-AzSynapseLinkConnectionLandingZoneCredential -SasToken "SampleSasToken"

This command updates the landing zone credential with sas token "exampleSasToken" of a link connection through pipeline.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.synapse/update-azsynapselinkconnectionlandingzonecredential>