



Red Hat Enterprise Linux Release 9.2 Manual Pages on 'devlink-dpipe.8' command

\$ man devlink-dpipe.8

DEVLINK-DPIPE(8) Linux DEVLINK-DPIPE(8)

NAME

devlink-dpipe - devlink dataplane pipeline visualization

SYNOPSIS

devlink [OPTIONS] dpipe { table | header } { COMMAND | help }

OPTIONS := { -V[ersion] }

devlink dpipe table show DEV [name TABLE_NAME]

devlink dpipe table set DEV name TABLE_NAME

devlink dpipe table dump DEV name TABLE_NAME

devlink dpipe header show DEV

devlink dpipe help

DESCRIPTION

devlink dpipe table show - display devlink dpipe table attributes

name TABLE_NAME

Specifies the table to operate on.

devlink dpipe table set - set devlink dpipe table attributes

name TABLE_NAME

Specifies the table to operate on.

devlink dpipe table dump - dump devlink dpipe table entries

name TABLE_NAME

Specifies the table to operate on.

devlink dpipe header show - display devlink dpipe header attributes

name TABLE_NAME

Specifies the table to operate on.

EXAMPLES

devlink dpipe table show pci/0000:01:00.0

Shows all dpipe tables on specified devlink device.

devlink dpipe table show pci/0000:01:00.0 name mlxsw_erif

Shows mlxsw_erif dpipe table on specified devlink device.

devlink dpipe table set pci/0000:01:00.0 name mlxsw_erif counters_en?

abled true

Turns on the counters on mlxsw_erif table.

devlink dpipe table dump pci/0000:01:00.0 name mlxsw_erif

Dumps content of mlxsw_erif table.

devlink dpipe header show pci/0000:01:00.0

Shows all dpipe headers on specified devlink device.

SEE ALSO

devlink(8), devlink-dev(8), devlink-monitor(8),

AUTHOR

Jiri Pirko <jiri@mellanox.com>

iproute2

4 Apr 2020

DEVLINK-DPIPE(8)