



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'OPENSSL_no_config.3ossl'

\$ man OPENSSL_no_config.3ossl

OPENSSL_CONFIG(3ossl) OpenSSL OPENSSL_CONFIG(3ossl)

NAME

OPENSSL_config, OPENSSL_no_config - simple OpenSSL configuration functions

SYNOPSIS

```
#include <openssl/conf.h>
```

The following functions have been deprecated since OpenSSL 1.1.0, and can be hidden entirely by defining OPENSSL_API_COMPAT with a suitable version value, see openssl_user_macros(7):

```
void OPENSSL_config(const char *appname);
```

```
void OPENSSL_no_config(void);
```

DESCRIPTION

OPENSSL_config() configures OpenSSL using the standard openssl.cnf and

reads from the application section appname. If appname is NULL then the default section, openssl_conf, will be used. Errors are silently ignored. Multiple calls have no effect.

OPENSSL_no_config() disables configuration. If called before OPENSSL_config() no configuration takes place.

If the application is built with OPENSSL_LOAD_CONF defined, then a call to OpenSSL_add_all_algorithms() will implicitly call OPENSSL_config() first.

NOTES

The OPENSSL_config() function is designed to be a very simple "call it and forget it" function. It is however much better than nothing.

Applications which need finer control over their configuration functionality should use the configuration functions such as CONF_modules_load() directly. This function is deprecated and its use should be avoided. Applications should instead call CONF_modules_load() during initialization (that is before starting any threads).

There are several reasons why calling the OpenSSL configuration routines is advisable. For example, to load dynamic ENGINES from shared libraries (DSOs). However, very few applications currently support the control interface and so very few can load and use dynamic ENGINES. Equally in future more sophisticated ENGINES will require certain control operations to customize them. If an application calls OPENSSL_config() it doesn't need to know or care about ENGINE control operations because they can be performed by editing a configuration file.

ENVIRONMENT

OPENSSL_CONF

The path to the config file. Ignored in set-user-ID and set-group-ID programs.

RETURN VALUES

Neither `OPENSSL_config()` nor `OPENSSL_no_config()` return a value.

SEE ALSO

`config(5)`, `CONF_modules_load_file(3)`

HISTORY

The `OPENSSL_no_config()` and `OPENSSL_config()` functions were deprecated in OpenSSL 1.1.0 by `OPENSSL_init_crypto()`.

COPYRIGHT

Copyright 2004-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7 2023-07-13 OPENSSL_CONFIG(3ossl)