



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'PKCS12_SAFEABAG_get_bag_nid.3ossl'

\$ man PKCS12_SAFEABAG_get_bag_nid.3ossl

PKCS12_SAFEABAG_GET1_CERT(3ossl) OpenSSL PKCS12_SAFEABAG_GET1_CERT(3ossl)

NAME

PKCS12_SAFEABAG_get0_attr, PKCS12_SAFEABAG_get0_type,
PKCS12_SAFEABAG_get_nid, PKCS12_SAFEABAG_get_bag_nid,
PKCS12_SAFEABAG_get0_bag_obj, PKCS12_SAFEABAG_get0_bag_type,
PKCS12_SAFEABAG_get1_cert, PKCS12_SAFEABAG_get1_crl,
PKCS12_SAFEABAG_get0_safes, PKCS12_SAFEABAG_get0_p8inf,
PKCS12_SAFEABAG_get0_pkcs8 - Get objects from a PKCS#12 safeBag

SYNOPSIS

```
#include <openssl/pkcs12.h>
```

```
const ASN1_TYPE *PKCS12_SAFEABAG_get0_attr(const PKCS12_SAFEABAG *bag,  
int attr_nid);
```

```
const ASN1_OBJECT *PKCS12_SAFEABAG_get0_type(const PKCS12_SAFEABAG *bag);
```

```
int PKCS12_SAFEABAG_get_nid(const PKCS12_SAFEABAG *bag);
```

```
int PKCS12_SAFEABAG_get_bag_nid(const PKCS12_SAFEABAG *bag);
```

```
const ASN1_TYPE *PKCS12_SAFEBAG_get0_bag_obj(const PKCS12_SAFEBAG *bag);
const ASN1_OBJECT *PKCS12_SAFEBAG_get0_bag_type(const PKCS12_SAFEBAG *bag);
X509 *PKCS12_SAFEBAG_get1_cert(const PKCS12_SAFEBAG *bag);
X509_CRL *PKCS12_SAFEBAG_get1_crl(const PKCS12_SAFEBAG *bag);
const STACK_OF(PKCS12_SAFEBAG) *PKCS12_SAFEBAG_get0_safes(const PKCS12_SAFEBAG *bag);
const PKCS8_PRIV_KEY_INFO *PKCS12_SAFEBAG_get0_p8inf(const PKCS12_SAFEBAG *bag);
const X509_SIG *PKCS12_SAFEBAG_get0_pkcs8(const PKCS12_SAFEBAG *bag);
```

DESCRIPTION

PKCS12_SAFEBAG_get0_attr() gets the attribute value corresponding to the attr_nid.

PKCS12_SAFEBAG_get0_type() gets the safeBag type as an OID, whereas PKCS12_SAFEBAG_get0_nid() gets the safeBag type as an NID, which could be NID_certBag, NID_crlBag, NID_keyBag, NID_secretBag, NID_safeContentsBag or NID_pkcs8ShroudedKeyBag.

PKCS12_SAFEBAG_get0_bag_nid() gets the type of the object contained within the PKCS12_SAFEBAG. This corresponds to the bag type for most bags, but can be arbitrary for secretBags.

PKCS12_SAFEBAG_get0_bag_type() gets this type as an OID.

PKCS12_SAFEBAG_get0_bag_obj() retrieves the object contained within the safeBag.

PKCS12_SAFEBAG_get1_cert() and PKCS12_SAFEBAG_get1_crl() return new X509 or X509_CRL objects from the item in the safeBag.

PKCS12_SAFEBAG_get0_p8inf() and PKCS12_SAFEBAG_get0_pkcs8() return the PKCS8 object from a PKCS8shroudedKeyBag or a keyBag.

PKCS12_SAFEBAG_get0_safes() retrieves the set of safeBags contained within a safeContentsBag.

RETURN VALUES

PKCS12_SAFEBAG_get_nid() and PKCS12_SAFEBAG_get_bag_nid() return the NID of the safeBag or bag object, or -1 if there is no corresponding NID. Other functions return a valid object of the specified type or NULL if an error occurred.

SEE ALSO

PKCS12_create(3), PKCS12_add_safe(3), PKCS12_add_safes(3)

COPYRIGHT

Copyright 2019-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7 2023-07-13 PKCS12_SAFEBAG_GET1_CERT(3openssl)