



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL_CTX_set_ssl_version.3ossl'

\$ man SSL_CTX_set_ssl_version.3ossl

SSL_CTX_SET_SSL_VERSION(3ossl) OpenSSL SSL_CTX_SET_SSL_VERSION(3ossl)

NAME

SSL_CTX_set_ssl_version, SSL_CTX_get_ssl_method, SSL_set_ssl_method,
SSL_get_ssl_method - choose a new TLS/SSL method

SYNOPSIS

```
#include <openssl/ssl.h>

int SSL_CTX_set_ssl_version(SSL_CTX *ctx, const SSL_METHOD *method);

const SSL_METHOD *SSL_CTX_get_ssl_method(const SSL_CTX *ctx);

int SSL_set_ssl_method(SSL *s, const SSL_METHOD *method);

const SSL_METHOD *SSL_get_ssl_method(const SSL *ssl);
```

DESCRIPTION

SSL_CTX_set_ssl_version() sets a new default TLS/SSL method for SSL objects newly created from this ctx. Most of the configuration attached to the SSL_CTX object is retained, with the exception of the configured TLS ciphers, which are reset to the default values. SSL objects already created from this SSL_CTX with SSL_new(3) are not affected, except when SSL_clear(3) is being called, as described below.

SSL_CTX_get_ssl_method() returns the SSL_METHOD which was used to

construct the SSL_CTX.

SSL_set_ssl_method() sets a new TLS/SSL method for a particular ssl object. It may be reset, when SSL_clear() is called.

SSL_get_ssl_method() returns a pointer to the TLS/SSL method set in ssl.

NOTES

The available method choices are described in SSL_CTX_new(3).

When SSL_clear(3) is called and no session is connected to an SSL object, the method of the SSL object is reset to the method currently set in the corresponding SSL_CTX object.

SSL_CTX_set_version() has unusual semantics and no clear use case; it would usually be preferable to create a new SSL_CTX object than to try to reuse an existing one in this fashion. Its usage is considered deprecated.

RETURN VALUES

The following return values can occur for SSL_CTX_set_ssl_version() and SSL_set_ssl_method():

0 The new choice failed, check the error stack to find out the reason.

1 The operation succeeded.

SSL_CTX_get_ssl_method() and SSL_get_ssl_method() always return non-NULL pointers.

SEE ALSO

SSL_CTX_new(3), SSL_new(3), SSL_clear(3), ssl(7),
SSL_set_connect_state(3)

HISTORY

SSL_CTX_set_ssl_version() was deprecated in OpenSSL 3.0.

COPYRIGHT

Copyright 2000-2022 The OpenSSL Project Authors. All Rights Reserved.
Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at
<<https://www.openssl.org/source/license.html>>.

