



Linux Ubuntu 26.04 Manual Pages on command 'gnuhead.1'

\$ man gnuhead.1

HEAD(1) User Commands HEAD(1)

NAME

head - output the first part of files

SYNOPSIS

head [OPTION]... [FILE]...

DESCRIPTION

Print the first 10 lines of each FILE to standard output. With more than one FILE, precede each with a header giving the file name.

With no FILE, or when FILE is -, read standard input.

Mandatory arguments to long options are mandatory for short options too.

-c, --bytes=[-]NUM

print the first NUM bytes of each file; with the leading '-', print all but the last

NUM bytes of each file

-n, --lines=[-]NUM

print the first NUM lines instead of the first 10; with the leading '-', print all

but the last NUM lines of each file

-q, --quiet, --silent

never print headers giving file names

-v, --verbose

always print headers giving file names

-z, --zero-terminated

line delimiter is NUL, not newline

--help display this help and exit

--version

output version information and exit

NUM may have a multiplier suffix: b 512, kB 1000, K 1024, MB 1000*1000, M 1024*1024, GB 1000*1000*1000, G 1024*1024*1024, and so on for T, P, E, Z, Y, R, Q. Binary prefixes can be used, too: KiB=K, MiB=M, and so on.

AUTHOR

Written by David MacKenzie and Jim Meyering.

REPORTING BUGS

GNU coreutils online help: <<https://www.gnu.org/software/coreutils/>>

Report any translation bugs to <<https://translationproject.org/team/>>

SEE ALSO

tail(1)

Full documentation <<https://www.gnu.org/software/coreutils/head>>

or available locally via: info '(coreutils) head invocation'

Packaged by Ubuntu (9.7-3ubuntu2)

Copyright ? 2025 Free Software Foundation, Inc.

License GPLv3+: GNU GPL version 3 or later <<https://gnu.org/licenses/gpl.html>>.

This is free software: you are free to change and redistribute it.

There is NO WARRANTY, to the extent permitted by law.

GNU coreutils 9.7

January 2026

HEAD(1)