



Linux Ubuntu 26.04 Manual Pages on command 'mkfontscale.1'

\$ man mkfontscale.1

MKFONTSCALE(1) General Commands Manual MKFONTSCALE(1)

NAME

mkfontscale - create an index of scalable font files for X

SYNOPSIS

```
mkfontscale [ -b ] [ -s ] [ -o filename ] [ -x suffix ] [ -a encoding ] ... [ -f fuzz ] [ -l
] [ -e directory ] [ -p prefix ] [ -r prefix ] [ -n prefix ] [ -u | -U ] [ -v ] [ -- ] [ di?
rectory ] ...
```

DESCRIPTION

For each directory argument, mkfontscale reads all of the scalable font files in the directory. For every font file found, an X11 font name (XLFD) is generated, and is written together with the file name to a file fonts.scale in the directory.

The resulting fonts.scale file should be checked and possibly manually edited before being used as input for the mkfontdir(1) program.

OPTIONS

- b read bitmap fonts. By default, bitmap fonts are ignored.
- s ignore scalable fonts. By default, scalable fonts are read. If -b is set, this flag has the side effect of enabling the reading of fonts.scale files.
- o filename
send program output to filename; default is fonts.scale if bitmap fonts are not being read, and fonts.dir if they are. If filename is relative, it is created in the directory being processed. If it is the special value -, output is written to standard output.
- x suffix

exclude all files with the specified suffix.

-a encoding

add encoding to the list of encodings searched for.

-f fuzz

set the fraction of characters that may be missing in large encodings to fuzz per?

cent. Defaults to 2%.

-l Write fonts.dir files suitable for implementations that cannot re-encode legacy fonts (BDF and PCF). By default, it is assumed that the implementation can re-encode Uni? code-encoded legacy fonts.

-e specifies a directory with encoding files. Every such directory is scanned for en? coding files, the list of which is then written to an "encodings.dir" file in every font directory.

-p Specifies a prefix that is prepended to the encoding file path names when they are written to the "encodings.dir" file. The prefix is prepended literally: if a '/' is required between the prefix and the path names, it must be supplied explicitly as part of the prefix.

-r Keep non-absolute encoding directories in their relative form when writing the "en? codings.dir" file. The default is to convert relative encoding directories to ab? solute directories by prepending the current directory. The positioning of this op? tions is significant, as this option only applies to subsequent -e options.

-n do not scan for fonts, do not write font directory files. This option is useful when generating encoding directories only.

-u, -U disable (-u) or enable (-U) indexing of ISO 10646:1 font encodings (default: en? abled).

-v print program version and exit.

-- end of options.

SEE ALSO

X(7), Xserver(1), mkfontdir(1), ttmkfdi(1), xfs(1), xset(1)

NOTES

The format of the fonts.scale, fonts.dir and encodings.dir files is documented in the mk? fontdir(1) manual page.

Mkfontscale will overwrite any fonts.scale file even if it has been hand-edited.

mkfontscale -b -s -l is equivalent to mkfontdir.

AUTHOR

The version of mkfontscale included in this X.Org Foundation release was originally written by Juliusz Chroboczek <jch@freedesktop.org> for the XFree86 project. The functionality of this program was inspired by the ttmkfdir utility by Joerg Pommnitz.

X Version 11

mkfontscale 1.2.3

MKFONTSCALE(1)